# **Remote Debugging**

## Remote Side (Without Visual Studio):

Get the correct remote tool : <a href="https://docs.microsoft.com/en-us/visualstudio/debugger/remote-debugging?view=vs-2015#get-the-remote-tools">https://docs.microsoft.com/en-us/visualstudio/debugger/remote-debugging?view=vs-2015#get-the-remote-tools</a>
OR

Copy "Remote Debugger folder" from local pc to remote, folder path at local: "C:\Program Files (x86)\Microsoft Visual Studio 14.0\Common7\IDE\Remote Debugger"

### OR

Share the "remote Debugger folder" (from local pc).

- 2. Configure Firewall
  - a) Open the Windows Firewall page. (In the **Start** menu search box, type **Windows Firewall**).
  - b) Click Allow an app or feature through Windows Firewall.
  - c) In the **Allowed apps and features** list, look for **Visual Studio Remote Debugger Discovery**. If it is listed, make sure that it is selected, and that one or more network types are also selected.
  - d) If **Visual Studio Remote Debugger Discovery** is not listed, click **Allow another app**. If you still don't see it in the **Add an app** window, click **Browse** and navigate to **Visual Studio installation directory>\Common7\IDE\Remote Debugger**. Find the appropriate folder for the application (x86, x64, Appx) and then select **msvsmon.exe**. Then click **Add**.
  - e) In the **Allowed apps and features** list, select **Visual Studio Remote Debugging Monitor**. Check one or more network types (**Domain**, **Home/Work (Private), Public**) that you want the remote debugging monitor to communicate with. The types must include the network to which the Visual Studio computer is connected.



## 3. Configure Ports in Firewall

- a. On the **Start** menu, search for **Windows Firewall with Advanced Security**.
- b. Click **Inbound Rules** and then click **New Rule** in the **Actions** list.
- c. On the **Rule Type** page, select **Port** and then click **Next**.
- d. On the **Protocol and Ports** page, select the port protocol (TCP or UDP). Select **Specific local ports** and enter one or more port numbers that you want to enable for the protocol. Separate numbers with commas. Then click **Next**.

Ports	Incoming/Outgoing	Protocol	Description
135, 139, 445	Outgoing	TCP	Required.
137, 138	Outgoing	UDP	Required.

- e. On the **Action** page, select **Allow the connection** and then click **Next**.
- f. On the **Profile** page, select one or more network types to enable for the port. The type you select must include the network to which the remote computer is connected. Then click **Next**.
- g. On the **Name** page, type a name for the rule, and then click **Finish**.
- h. You should see your new rule in the **Inbound Rules** or **Outbound Rules** list.


### 4. Run Remote Debugger server

a. Run "msvsmon.exe" as Administrator in remote debugger folder.




## **Local Side (With Visual Studio)**

- 1. Configure Firewall
  - a. Repeat the same as in "Remote Side: Configure firewall".
- 2. Configure ports in Firewall
  - a. Repeat the same as in "Remote Side: Configure ports in firewall" with ports: (TCP: 135), (UDP: 500, 4500).
- 3. Run Visual Studio as "Remote Windows Debugger"
  - a. Configure the project properties as following:



b. Run in "Remote Windows Debugger"



### Reference:

https://docs.microsoft.com/en-us/visualstudio/debugger/remote-debugging?view=vs-2015

https://docs.microsoft.com/en-us/visualstudio/debugger/configure-the-windows-firewall-for-remote-debugging?view=vs-2015